

CUPS - plik konfiguracyjny (laptop)

Położenie: /etc/cups/cupsd.conf

© 3bird Projects 2007, <http://3bird.net>

ServerName acer.imagine
ServerAdmin robertSurma@3bird.net
LogLevel info

PreserveJobHistory Yes
PreserveJobFiles No
AutoPurgeJobs No
MaxPrinterHistory 10
Opcje wydruku dla użytkownika:

MaxCopies 40
MaxJobs 10
MaxJobsPerPrinter 10
MaxJobsPerUser 10

SystemGroup lpadmin

Serwer startuje na prawach:

User lp
Group sys
Port 631
Listen /var/run/cups/cups.sock

Wyszukiwanie drukarek w sieci

Browsing On
BrowseOrder allow,deny
BrowseAllow @LOCAL

DefaultAuthType Digest

<Location />

Order allow,deny

Allow @LOCAL

</Location>

<Location /admin>

Encryption Required

Order allow,deny

Allow @LOCAL

</Location>

<Location /admin/conf>

Encryption Required

Order allow,deny

Allow @LOCAL

</Location>

<Policy default>

<Limit Send-Document Send-URI Hold-Job Release-Job Restart-Job Purge-Jobs Set-Job-Attributes
Create-Job-Subscription Renew-Subscription Cancel-Subscription Get-Notifications Reprocess-Job
Cancel-Current-Job Suspend-Current-Job Resume-Job CUPS-Move-Job>

Require user @OWNER @SYSTEM

Order deny,allow

</Limit>

<Limit Pause-Printer Resume-Printer Set-Printer-Attributes Enable-Printer Disable-Printer Pause-Prin-

ter-After-Current-Job Hold-New-Jobs Release-Held-New-Jobs Deactivate-Printer Activate-Printer
Restart-Printer Shutdown-Printer Startup-Printer Promote-Job Schedule-Job-After CUPS-Add-Printer
CUPS-Delete-Printer CUPS-Add-Class CUPS-Delete-Class CUPS-Accept-Jobs CUPS-Reject-Jobs
CUPS-Set-Default>

```
AuthType Basic
Require user @SYSTEM
Order deny,allow
</Limit>
<Limit CUPS-Authenticate-Job>
Require user @OWNER @SYSTEM
Order deny,allow
</Limit>
<Limit Cancel-Job>
Order deny,allow
Require user @OWNER @SYSTEM
</Limit>
<Limit All>
Order deny,allow
</Limit>
</Policy>
```

Ostatnia aktualizacja: 27 marzec 2007.