

inittab – plik konfiguracyjny

Położenie: /etc/inittab

© Imagine Studio 2004, <http://mygentoo.of.pl>

```
#
# /etc/inittab: This file describes how the INIT process should set up
# the system in a certain run-level.
#
# Author: Miquel van Smoorenburg, <miquels@cistron.nl>
# Modified by: Patrick J. Volkerding, <volkerdi@ftp.cdrom.com>
# Modified by: Daniel Robbins, <dروbbins@gentoo.org>
# Modified by: Martin Schlemmer, <azarah@gentoo.org>
#
# $Header: /home/cvsroot/gentoo-src/rc-scripts/etc/inittab,v 1.6 2003/01/06 21:32:43 azarah Exp $

# Default runlevel.
id:3:initdefault:

# System initialization, mount local filesystems, etc.
si::sysinit:/sbin/rc sysinit

# Further system initialization, brings up the boot runlevel.
rc::bootwait:/sbin/rc boot

I0:0:wait:/sbin/rc shutdown
I1:S1:wait:/sbin/rc single
I2:2:wait:/sbin/rc nonetwork
I3:3:wait:/sbin/rc default
I4:4:wait:/sbin/rc default
I5:5:wait:/sbin/rc default
I6:6:wait:/sbin/rc reboot
#z6:6:respawn:/sbin/sulogin

# TERMINALS
c1:12345:respawn:/sbin/agetty 38400 tty1 linux
c2:12345:respawn:/sbin/agetty 38400 tty2 linux
c3:12345:respawn:/sbin/agetty 38400 tty3 linux
c4:12345:respawn:/sbin/agetty 38400 tty4 linux
c5:12345:respawn:/sbin/agetty 38400 tty5 linux
c6:12345:respawn:/sbin/agetty 38400 tty6 linux

# What to do at the "Three Finger Salute".
ca:12345:ctrlaltdel:/sbin/shutdown -r now

# Used by /etc/init.d/xdm to control DM startup.
# Read the comments in /etc/init.d/xdm for more
# info. Do NOT remove, as this will start nothing
# extra at boot if /etc/init.d/xdm is not added
# to the "default" runlevel.
x:a:once:/etc/X11/startDM.sh

# End of /etc/inittab
```

Ostatnia aktualizacja: 12 wrzesień 2004.